



# INSTA LOOPER V.1.2



## 1. Presentation :

INSTA LOOPER, is a looper, but not only.

This tool allows you to loop your music with many different sizes, to pitch your loop, put some integrated FX on it and reverse it.

This tool is useful for making Live Fx, or to program them when you create your tune.

## 2. Installation :

Extract the **InstaLooperVST-x86-v1.2** or **InstaLooperVST-x64-v1.2** from the zip archive and copy the file in your VST path 32 bit or 64 bit plugins folder.

The plugin should appear in your host (after VST scanning or rescanning) under the name "**InstaLooperVST-x86**" or "**InstaLooperVST-x64**"

## 3. Using the plugin

You have two ways to click on this plugin.

If you are using the "left click" on the push buttons LOOP, FX and REV you will see that the functions are enabled only when you hold the click on.

If you are using the "right click" on the push buttons LOOP, FX and REV, the push button will be toggled, so you have "right click" again to deactivate it.

### 3.1 LOOP Parameters

- LOOP on/off:



**Left click** on the on/off button to activate the loop.

The loop function will stay activated as long as you hold the button.

When you release the button, the loop is deactivated.

**Right click** on the on/off button to activate the loop. **Right click** again to deactivate the loop.

- **SIZE**



This knob defines the Size of the loop:

1 Bar

2 beat

1 beat

3 / 4 beat

1 / 2 beat

3 / 8 beat

1 / 4 beat

1 / 8 beat

1 / 16 beat

1 / 32 beat

- **FX on/off**



**Left click** on the on/off button to activate FX.

The FX function will stay activated as long as you hold the button.

When you release the button, FX are deactivated.

**Right click** on the on/off button to activate the FX. **Right click** again to deactivate the FX.

- **SPEED**



This knob defines the speed rate of the loop, works like a linear pitch.

50 stands for half speed.

100 is the default value

200 stands for double speed.

- REV



**Left click** on the on/off button to activate the loop reverse, the reverse function will stay activated as long as you hold the button.

When you release the button, the loop is deactivated.

**Right click** on the on/off button to activate the loop reverse. **Right click** again to deactivate the reverse.

## 4. Select the FX



**Right click** on each loop panel to show the FX select menu of selected loop.

Each loop have four integrated FX available to select.

**Bit Reducer** : works like a crusher effect.

**Autopan**: is a panoramic effect. The Autopan range follows the loop size.

*Example: loop size is on 1 / 4 activated, the Autopan will be fixed on 1 / 4 automatically. If you change the loop size, Autopan range will be affected accordingly.*

**Hipass**: When enabled, this apply a fixed Hipass filter.

**Phazer**: When enabled, this apply a fixed phazer effect.

**Time Expand**: expand the time of your loop without changing the pitch, in the same old fashion as first samplers.

Enjoy! 😊

AUDIO BLAST TEAM

Bugged plugins for bugged people.